

WinFlow & WinTran Update / Installation Instructions:

Following are instructions for performing an update or fully installing WinFlow and WinTran. If it has been over a year since you updated your software, or if you have not updated your WinFlow to the 32 Bit version from the 16 Bit version first posted in December 2002, you should perform a new installation of the software. Otherwise, you may simply choose to update your WinFlow and WinTran directories. If installing both applications, we recommend that you install WinFlow first.

Before beginning an update or new installation, remember to create a temporary folder on your hard drive in which to download the files from the Internet. Once the update or install files are copied into the temporary folder, unzip the downloaded file into the temporary folder using the current passwords. Among the files that will be extracted from the downloaded file will be either an "install.zip" file or "update.zip" file depending on which process you have selected. This process will be the same for WinFlow or WinTran.

Software Update Instructions:

To perform a software update, simply unzip the "update.zip" file directly into your existing WinFlow or WinTran folder allowing any updated files to be overwritten. No password is required to unzip these secondary ZIP files. Once completed, the latest version of WinFlow or WinTran will be installed.

Software Installation Instructions:

Before beginning an installation, you first need to locate a complete set of ID files for WinFlow and/or WinTran and know the location of these files. (Please see additional notes on ID files below). To perform a full installation, unzip the "install.zip" file into the temporary folder allowing all of the files in the zip file to extract. Next locate and double click the "setup.exe" file to begin the installation. The Installation Wizard will begin the installation and prompt you for the location of the ID files. It will then install WinFlow and/or WinTran in the default directory c:\greggeng\ which will be created on your hard drive. You will have to give the location of the ID files to the Installation Wizard by selecting the location directory in the "pop up" window. The ID files can be located in any directory on your hard drive, a floppy disk or a CD. However, they must all be in the same directory.

ID Files:

The ID files are small "text" files which activate the software to work in conjunction with the protection key which you have been issued. To perform a full installation, you will need a complete set of ID files, including the "instinfo.ini" file set for either WinFlow or WinTran. If you do not have the necessary ID files, please contact us by telephone or email.

Listed below are the basic ID files required to install WinFlow and WinTran:

WinFlow: ctrlcode.id, datamgr.id, instinfo.ini

WinTran: ctrlcode.id, wintran.id, instinfo.ini

After updating or installing the software, you can check the version number by selecting “Help” and “About” from either the WinFlow or WinTran menu bar. The version number should match the one currently listed on our website.

For additional assistance performing a software update or installation, please contact us by telephone at 281.494.8100 or by email at office@greggengineering.com.